

## Advanced Visual FoxPro To RTF Table Converter

### Product Information Page:

[http://www.advancedreliablesoftware.com/advanced\\_visual\\_fox\\_pro\\_to\\_rtf\\_table\\_converter.html](http://www.advancedreliablesoftware.com/advanced_visual_fox_pro_to_rtf_table_converter.html)

**Advanced Visual FoxPro To RTF Table Converter** is a utility that allows execution of SQL (Structured Query Language) queries on Visual FoxPro DBF database files. Resultsets returned by select SQL queries are automatically persisted as RTF table files to a directory of your choice.

### Step 1 – Input File

Click the "Select Input Visual FoxPro DBF File" button and browse to your input DBF file.



### Step 2 – SQL Select Query

Enter your SQL select query. Enclose any column names that contain space character in "[, "]" brackets.

Examples:

Select all columns from DBF file named "sample.dbf".

**select \* from "DBF file path";**



Select columns with column names "LastName", "FirstName", "Title" from DBF file named "sample.dbf".

**select LastName, FirstName, Title from "DBF file path";**



Select columns with column names "Last Name", "First Name", "Title" from DBF file named "sample.dbf".

**select [Last Name], [First Name], Title from "DBF file path";**

Step 2 - SQL Select Query

```
select [Last Name], [First Name], Title
from "C:\Documents and Settings\Administrator\Desktop\sample.dbf"
```

### Step 3 (Optional) – Column Headers

Check the "Insert Column Headers" check box to include table column headers in your output RTF document. Define one header for each column in your SQL query. To add new column header enter desired information in the input field and click the "Add Column Header" button. To remove specific column header select it in the grid and click the "Remove Column Header" button.

Step 3 (Optional) - Column Headers

Insert Column Headers

Column Headers	
Last Name	
First Name	
Title	

**Add Column Header**

**Remove Column Header**

Sample RTF output file table column headers:

Last Name	First Name	Title
Davolio	Nancy	Sales Representative
Fuller	Andrew	Vice President, Sales
Leverling	Janet	Sales Representative

#### Step 4 – Output RTF File Properties

Define properties of the output RTF document: page size, page orientation, font, font size.

Step 4 - Output RTF File Properties

RTF Page Size: Letter

RTF Page Orientation:  Portrait  Landscape

RTF Font: Arial  RTF Font Size: 12

#### Step 5 – Output Directory

Click the “...” button to assign output directory path. The application will automatically persist your most recently used output directory path for future reference.

Step 5 - Output Directory

C:\Documents and Settings\Administrator\My Documents

#### Step 6 (Optional) – Output RTF File Name

Assign custom name for your RTF output file.

Step 6 (Optional) - Output RTF File Name

Output RTF File Name:

#### Step 7 – Execute SQL Query / Generate RTF Output

Click the “Execute SQL Query / Generate RTF Output” button to execute SQL query on your input file and generate an output RTF document. Your RTF output document will be created in the directory defined in Step 5.

Step 7 - Execute SQL Query / Generate RTF Output

Sample RTF output:

Last Name	First Name	Title
Davolio	Nancy	Sales Representative
Fuller	Andrew	Vice President, Sales
Leverling	Janet	Sales Representative