

## Reliable E-Mail Alerter

### Product Information Page:

[http://www.advancedreliablesoftware.com/reliable\\_email\\_alerter.html](http://www.advancedreliablesoftware.com/reliable_email_alerter.html)

**Reliable E-Mail Alerter** is a scriptable SMTP e-mail client utility that sends out pre-configured e-mail messages.

Default installation path:

32-bit operating system

"C:\Program Files\AdvancedReliableSoftware\  
ReliableEmailAlerter\ReliableEmailAlerter.exe"

64-bit operating system

"C:\Program Files (x86)\AdvancedReliableSoftware\  
ReliableEmailAlerter\ReliableEmailAlerter.exe"

### Step 1 – Create XML Configuration File

Execute ReliableEmailAlerter.exe in order to create an XML configuration file, ReliableEmailAlerter.xml, populated with default settings.

The XML configuration file will be created in one of the below folders, depending on your operating system:

My Documents\AdvancedReliableSoftware\ReliableEmailAlerter

Documents\AdvancedReliableSoftware\ReliableEmailAlerter

### Step 2 – Modify XML Configuration File

**EmailServer** - SMTP server name or IP address.

**Port** – SMTP port.

**EmailAccount** – E-mail account valid on the above SMTP server.

**EmailAccountPassword** – E-mail account password.

**FromEmailAddresses** - Comma separated list of From e-mail addresses.

**ToEmailAddresses** - Comma separated list of To e-mail addresses.

**CCEmailAddresses** - Comma separated list of CC e-mail addresses.

**EmailSubject** - Message subject.

**EmailBody** - Message body.

**AttachmentPaths** – Container for one or more attachment paths.

**AttachmentPath** – Fully qualified path to the attachment file.

Sample ReliableEmailAlerter.xml:

```
<?xml version="1.0" encoding="UTF-8" ?>
<ReliableEmailAlerter>
  <MACAddress />
  <ActivationCode />
  <OtherActivationCodes />
  <EmailServer>smtp.yourdomain.com</EmailServer>
  <Port>587</Port>
  <EmailAccount />
  <EmailAccountPassword />
  <FromEmailAddresses>from@localhost</FromEmailAddresses>
  <ToEmailAddresses>to@localhost</ToEmailAddresses>
  <CCEmailAddresses />
  <EmailSubject>E-mail subject.</EmailSubject>
  <EmailBody>E-mail body.</EmailBody>
  - <AttachmentPaths>
    <AttachmentPath />
    <AttachmentPath />
    <AttachmentPath />
    <AttachmentPath />
    <AttachmentPath />
  </AttachmentPaths>
</ReliableEmailAlerter>
```

### Step 3 (Optional) – 64-bit Windows Operating Systems

On 64-bit Windows operating systems the application will be installed to

C:\Program Files (x86)\AdvancedReliableSoftware directory.

On 64-bit Windows operating systems use below path to execute the application:

"C:\Program Files (x86)\AdvancedReliableSoftware\  
ReliableEmailAlerter\ReliableEmailAlerter.exe"